

Grandstream Device Configuration

STATUS BASIC SETTINGS ADVANCED SETTINGS 1 ADVANCED SETTINGS 2

Onhook Threshold:

FXS Impedance:

Caller ID Scheme:

Onhook Voltage:

Polarity Reversal: ☒ No ☐ Yes (reverse polarity upon call establishment and termination)

NTP Server: (URI or IP address)

Send Anonymous: ☒ No ☐ Yes (caller ID will be blocked if set to Yes)

Anonymous Method: ☒ Use From Header ☐ Use Privacy Header

Time to ring:

Special Feature:

CBCOM Encode SIP RT(C)P T38

CBCOM Encoder 1.1 Key: (not shown for security reason)

Syslog Server:

Syslog Level:

Session Expiration: (in seconds. default 180 seconds)

Min-SE: (in seconds. default and minimum 90 seconds)

Caller Request Timer: ☐ Yes ☒ No (Request for timer when making outbound calls)

Callee Request Timer: ☐ Yes ☒ No (When caller supports timer but did not request one)

Force Timer: ☐ Yes ☒ No (Use timer even when remote party does not support)

UAC Specify Refresher: ☐ UAC ☐ UAS ☒ Omit (Recommended)

UAS Specify Refresher: ☒ UAC ☐ UAS (When UAC did not specify refresher tag)

Force INVITE: ☐ Yes ☒ No (Always refresh with INVITE instead of UPDATE)

Firmware Upgrade and Provisioning: Upgrade Via ☐ TFTP ☒ HTTP

Firmware Server Path:

Configure Server Path:

Firmware File Prefix:

Firmware File Postfix:

Config File Prefix:

Config File Postfix:

Retry-after(minutes): if server unavailable

Automatic Upgrade:

☐ No ☒ Yes, check upgrade every minutes (default 7 days)

☒ Always Check for New Firmware

☐ Check New Firmware only when F/W pre/suffix changes

☐ Always Skip the Firmware Check

Firmware Key: (in Hexadecimal Representation)

Authenticate Conf File: ☒ No ☐ Yes (cfg file would be authenticated before acceptance if set to Yes)

Lock keypad update: ☒ No ☐ Yes (configuration update via keypad is disabled if set to Yes)

Allow conf SIP Account in Basic Settings: ☒ No ☐ Yes

Override MTU Size:

Volume Amplification: TX RX

Powerline Ring Tone: Frequency (Hz) ON (x10ms) OFF (x10ms)
(Allowed: 15-100) (Allowed: 5-800) (Allowed: 5-800)

Call Progress Tones:	Frequency 1 (Hz)	Frequency 2 (Hz)	ON (x10ms) (C1;C2;C3)	OFF (x10ms) (C1;C2;C3)
Dial Tone	<input type="text" value="350"/>	<input type="text" value="440"/>	<input type="text" value="0"/>	<input type="text" value="0"/>
Recall Dial Tone	<input type="text" value="350"/>	<input type="text" value="440"/>	<input type="text" value="10"/>	<input type="text" value="10"/>
Message Waiting	<input type="text" value="350"/>	<input type="text" value="440"/>	<input type="text" value="10"/>	<input type="text" value="10"/>
Confirmation	<input type="text" value="350"/>	<input type="text" value="440"/>	<input type="text" value="10"/>	<input type="text" value="10"/>
Audible Ringing	<input type="text" value="440"/>	<input type="text" value="480"/>	<input type="text" value="200"/>	<input type="text" value="400"/>
Busy Tone	<input type="text" value="480"/>	<input type="text" value="620"/>	<input type="text" value="50"/>	<input type="text" value="50"/>
Reorder Tone	<input type="text" value="480"/>	<input type="text" value="620"/>	<input type="text" value="25"/>	<input type="text" value="25"/>
Receiver Offhook Tone	<input type="text" value="1400"/>	<input type="text" value="2600"/>	<input type="text" value="10"/>	<input type="text" value="10"/>

Disable Line Echo Canceller (LEC): ☒ No ☐ Yes (If set Yes, echo canceller is not used)

Disable voice prompt: ☒ No ☐ Yes (voice prompt is disabled if set Yes)

Enable Toll Application: ☒ No ☐ Yes (Default No, set to Yes if connecting to toll pay device or phone)

All Rights Reserved Grandstream Networks, Inc. 2005